



# Tetra4D Enrich

## Version 2021 SP1

### Release Notes

Details of new features, updated format support and bug fixes for Tetra4D Enrich

# Table of Contents

- Version 2021 SP1 .....3
  - Definition of Release Types..... 3
  - Version Information..... 3
  - Installation ..... 3
  - Language Support Overview..... 3
  - Acrobat Pro Compatibility .....4
- System Requirements ..... 4
- Licensing ..... 5
  - Message for Tetra4D Enrich existing customers ..... 5
  - New Tetra4D Enrich customers ..... 5
  - Information about the licensing management solution ..... 6
- Format Support..... 7
- Updated formats support and Reader/Writer enhancements..... 9
  - CAD Reader: Catia V5..... 9
  - CAD Reader: JT..... 9
  - CAD Reader: Parasolid ..... 9
  - CAD Reader: Creo ..... 9
  - CAD Reader: Rhino..... 9
  - CAD Reader: Siemens/NX ..... 9
- Bug Fixes ..... 9

# Version 2021 SP1

## Definition of Release Types

We define each release type as follows:

- **Major release:** A major release associated with an incremented release number (e.g. 2019) and an approximate 12 months' product cycle.
- **Minor release:** An update between major releases that may include support for new file formats, new versions of currently supported formats, and bug fixes. These updates are Service Packs (SP), and are defined with an additional incremented number put aside the major release information (e.g. 2019.1 for the first Service pack of release 2019)
- **Out of cycle patch:** An unscheduled update. These contain few functional updates with the intention to limit impact.

## Version Information

Item	Version Number
Tetra4D Enrich	2021.1.x

Notice that the third number is used to differentiate builds of the software, and may not be continuous.

## Installation

This version can be installed over any prior installation of Tetra4D Enrich. For more installation information, please refer to the [Tetra4D Enrich Installation Guide](#) or visit our [Learning page](#).

## Language Support Overview

Tetra4D Enrich provides support for multiple languages as noted in the table below. However, the language used is controlled by the local Adobe® Acrobat® installation. If there is a Tetra4D Enrich language option that matches the Acrobat installation, then that language is used; if not, Tetra4D Enrich defaults to English.

Tier 1 and Tier 2 are as defined by Adobe Systems.

Tier	Tetra4D Enrich Supported Languages
Tier 1	English, French, German, Japanese
Tier 2	Brazilian Portuguese, Italian, Korean, Spanish, Simplified Chinese

## Acrobat Pro Compatibility

The Tetra4D Enrich is a plug-in for Adobe Acrobat Pro. The following table provides information about tested version compatibility. Note that older versions of Tetra4D Enrich may work with newer Acrobat Pro releases, even if compatibility is not explicitly mentioned here.

Tetra4D Enrich	Compatible Acrobat Pro DC / 2017 / 2020 Versions
<b>2021.1</b>	Acrobat Pro 2020: 2020.000.0000 - to 2020.004.30006 (Classic track) Acrobat Pro 2017: 2017.000.0000 - to 2017.011.30199 (Classic track) Acrobat Pro DC: 2015.000.00000 - to 2015.006.30527 (Classic track) - to 2021.005.20058 (Continuous track)

Note:

The ADOBE Products and technical support periods can be found [here](#).

## System Requirements

Please refer to the [Tetra4D Enrich Installation Guide](#) to access to the system requirements.

# Licensing

## Message for Tetra4D Enrich existing customers

**Tetra4D Enrich 2021 SP1** is a minor release, and doesn't require a new license if you already installed and licensed **Tetra4D Enrich 2021**.

If you didn't already install and license **Tetra4D Enrich 2021**, you will need to change your license and activate the seats when **Tetra4D Enrich 2021 SP1** is installed.

Notice that if you are under regular maintenance, you should automatically receive information to retrieve your serial number for **Tetra4D Enrich 2021**, in an email from tetra4d.com.

Please carefully read the [Tetra4D Enrich Installation Guide](#) for explanations on how to activate your licenses.

## New Tetra4D Enrich customers

You should have automatically received information to retrieve your serial number for **Tetra4D Enrich 2021**, in an email from tetra4d.com.

Please carefully read the [Tetra4D Enrich Installation Guide](#) for instructions on how to activate your licenses.

Note: Tetra4D Enrich will run in trial mode for 28 days after completing the installation, providing you with the ability to use the product temporarily without a serial number.

You will have full functionality of the software during the trial period. If you experience any problem during the installation and activation process, please contact support by visiting our [Learning page](#).

## Information about the licensing management solution

The licensing management solution for **Tetra4D Enrich** offers flexibility and autonomy for customers to manage their licenses:

- Licensing Tetra4D Enrich can be done directly by customers, without requiring customers to contact Tetra4D support
- Online and offline activations are supported
  - Online activation requires a few actions and is fully performed within the product (no support request, no email communication)
  - In case of offline activation, information to activate the seat has to be communicated through email via submitting a support ticket.
- Activation / deactivation is enabled making it possible to transfer a license from one system to another
  - In cases where a system / license is no longer used and has to be transferred to another one
  - The transfer can be performed directly by the customer

Note:

- The transfer of a license has to be occasional, and is allowed in case of:
  - Computer crash
  - Computer change

The Tetra4D support team is available to answer any questions and to assist whenever needed. To receive assistance from the support team, please contact support by visiting our [Learning page](#).

## Format Support

This release supports **reading** the following 3D file formats:

Format	Version	Extensions
ACIS (SAT)	Up to version 2020	SAT, SAB
Autodesk AutoCAD (3D only)	Up to v2019	DWG, DXF
Autodesk DWF	Any	DWF, DWFX
Autodesk Inventor	Up to 2021	IPT, IAM
CATIA V4	Up to 4.2.5	MODEL, SESSION, DLV, EXP
CATIA V5	R4 to <b>V5_6R2021</b>	CATDrawing, CATPart, CATProduct, CATShape, CGR
CATIA V6	Up to V5-6 R2019 (R29)	3DXML
FBX	ASCII: from 7100 to 7400. Binary: all	FBX
GL Transmission format	2.0	GLTF, GLB
I-deas	Up to 13.x (NX 5), NX I-deas 6	MF1, ARC, UNV, PKG
IGES	5.1, 5.2, 5.3	IGS, IGES
Industry Foundation Classes (IFC)	IFC2x Editions 2, 3 and 4	IFC, IFCZIP
JT	<b>Up to version 10.5</b>	JT
Parasolid (X_T)	<b>Up to v33.1</b>	X_B, X_T, XMT, XMT_TXT
PRC	All Versions	PRC
PTC Creo	Pro/Engineer 19.0 to <b>Creo 8.0</b>	ASM, NEU, PRT, XAS, XPR
PTC Pro/Engineer	Up to Wildfire 5	ASM, NEU, PRT, XAS, XPR
REVIT	2015 to 2021	RVT, RFA
Rhino	4, 5, 6, <b>7</b>	3DM
Siemens PLM Software NX	V11.0 to NX 12, and up to <b>NX 1980</b>	PRT
Solid Edge	V19 - 20, ST – ST10, 2021	ASM, PAR, PWD, PSM
SolidWorks	Up to 2021	SLDASM, SLDPRT
STEP	AP 203 E1/E2, AP 214, AP 242	STP, STEP, STPZ
STEP XML	All versions	STPX, STPXZ
Stereo Lithography (STL)	All Versions	STL
Universal 3D (U3D)	ECMA-363 (1 <sup>st</sup> to 3 <sup>rd</sup> editions)	U3D
VDA-FS	Version 1.0 and 2.0	VDA
VRML	V1.0 and V2.0	WRL, VRML
Wavefront	Any	OBJ

This release supports **writing** the following 3D file formats:

Format	Extensions
<b>3MF</b>	3MF
<b>ACIS</b>	SAT, SAB
<b>FBX</b>	FBX
<b>IGES</b>	IGS, IGES
<b>JT</b>	JT
<b>Parasolid</b>	X_T
<b>PRC</b>	PRC
<b>STEP</b>	STP, STEP, STP.Z
<b>Stereo Lithography (STL)</b>	STL
<b>Universal 3D (U3D)</b>	U3D
<b>VRML</b>	WRL, VRML
<b>Wavefront</b>	OBJ



## Updated formats support and Reader/Writer enhancements

This section outlines the CAD Readers and Writers that have been added or improved in this new Tetra4D Enrich release.

### CAD Reader: Catia V5

- Support for version V5\_6R2021

### CAD Reader: JT

- Support for version 10.5

### CAD Reader: Parasolid

- Support for version 33.1

### CAD Reader: Creo

- Support for version 8.0

### CAD Reader: Rhino

- Support for version 7

### CAD Reader: Siemens/NX

- Support for version 1980

## Bug Fixes

The 2021 SP1 release of the Tetra4D Enrich fixes several customers' reported issues. Please contact support by visiting our support page if you have questions about any specific issue.